Console_Driver V 1.0.0

By Kunal Salvi

1 Console Module for STM32F407VGT6	3
1.1 Introduction	3
1.2 Features	3
1.3 Dependencies	3
1.4 Usage	4
2 File Index	5
2.1 File List	5
3 File Documentation	7
3.1 Console.c	7
3.2 Console.h File Reference	8
3.3 Console.h	9
Index	11

Chapter 1

Console Module for STM32F407VGT6

1.1 Introduction

The Console module provides an abstraction layer for UART communication on the STM32F407VGT6 microcontroller. It is designed for efficient data handling using DMA and provides easy-to-use functions for formatted printing and reading through a serial interface.

1.2 Features

- · UART initialization with custom baud rate
- Formatted printing using printConsole
- Formatted input using readConsole
- · DMA-based UART reception for high efficiency
- · Designed to support common debugging and communication tasks

1.3 Dependencies

The Console module depends on the following components:

- · GPIO for UART pin configuration
- · USART for UART initialization and communication
- · DMA for efficient UART data handling

Include the following headers in your project to use the Console module:

- Console.h
- GPIO.h (for GPIO configuration)
- USART.h (for UART initialization and communication)
- DMA.h (for DMA configuration)

1.4 Usage

To use the Console module, include the <code>Console.h</code> header in your application code. Initialize the console with a desired baud rate using <code>Console_Init</code>. Use <code>printConsole</code> for sending formatted messages and <code>readeConsole</code> for receiving formatted input.

Example:

```
int main(void) {
   Console_Init(9600); // Initialize UART with 9600 baud rate
   printConsole("Hello, STM32!\n"); // Send a message
   char buffer[20];
   readConsole("%s", buffer); // Read user input into buffer
   printConsole("You entered: %s\n", buffer); // Echo the input
   while (1) {
        // Application code
   }
}
```

Chapter 2

File Index

2.1 File List

Here is a list of all documented files with brief descriptions:

Console.c	 7
Console.h	
Console Interface for STM32F407VGT6	 3

6 File Index

Chapter 3

File Documentation

3.1 Console.c

```
00001 #include "Console.h"
00002
00003 // Flags to control and monitor UART reception
00004 volatile int rx\_get\_flag = 0; // Indicates if the reception is active 00005 volatile int rx\_flag = 0; // Indicates if data reception is complete
00006
00007 #define RX_Buffer_Length 100 // Length of the reception buffer
00008
00009 // Variables to track the length of received data and the reception buffer
00010 volatile int RX_Length = 0;
00011 volatile char TRX_Buffer[RX_Buffer_Length]; // Buffer for received and transmitted data
00012
00013 // USART configuration structure
00014 USART_Config serial;
00015
00016
00017
00025 void UART4 IROHandler(void) {
        00026
00028
               (void) UART4->DR; // Read the data register to clear flags
00029
00030
              __disable_irq(); // Disable interrupts to safely update DMA configurations
00031
00032
              // Disable DMA stream
00033
              serial.USART_DMA_Instance_RX.Request.Stream->CR &= ~DMA_SxCR_EN;
00034
00035
               // Calculate the length of received data
00036
              RX_Length = RX_Buffer_Length - serial.USART_DMA_Instance_RX.Request.Stream->NDTR;
00037
00038
              // Prevent buffer overflow
              if (RX_Length > RX_Buffer_Length) {
   RX_Length = RX_Buffer_Length;
00039
00040
00041
00042
              // Reset DMA stream for the next reception
00043
              serial.USART_DMA_Instance_RX.Request.Stream->NDTR = RX_Buffer_Length;
00044
00045
              serial.USART_DMA_Instance_RX.Request.Stream->CR |= DMA_SxCR_EN;
00046
00047
              __enable_irq(); // Re-enable interrupts
00048
00049
              rx_flag = 1; // Set the flag indicating data reception is complete
00050
00051 }
00052
00053
00062 void Console_Init(int32_t baudrate) {
00063
          // Reset USART configuration to default values
00064
          USART_Config_Reset(&serial);
00065
00066
          // Configure USART parameters
00067
          serial.Port = UART4; // Use UART4 for console communication
00068
          serial.baudrate = baudrate; // Set the baud rate
00069
          serial.mode = USART_Configuration.Mode.Asynchronous; // Asynchronous mode
00070
          serial.stop_bits = USART_Configuration.Stop_Bits.Bit_1; // 1 stop bit
          serial.TX_Pin = UART4_TX_Pin.PC10; // TX pin is PC10 serial.RX_Pin = UART4_RX_Pin.PC11; // RX pin is PC11
00071
00072
          serial.interrupt = USART_Configuration.Interrupt_Type.IDLE_Enable; // Enable IDLE interrupt
```

8 File Documentation

```
serial.dma_enable = USART_Configuration.DMA_Enable.TX_Enable |
      USART_Configuration.DMA_Enable.RX_Enable; // Enable DMA for TX and RX
00075
00076
          // Initialize USART
          if (USART_Init(&serial) != true) {
00077
              // Handle USART initialization failure (e.g., log error or halt execution)
00078
00079
00080 }
00081
00082
       void printConsole(char *msg, ...) {
00092
00093
           va_list args;
00094
           va start (args, msg);
00095
00096
           \ensuremath{//} Format the message and store it in the transmission buffer
00097
           vsprintf((char *)TRX_Buffer, msg, args);
00098
00099
           // Get the length of the formatted string
           uint16_t len = strlen((char *)TRX_Buffer);
00100
00101
00102
            // Transmit the buffer using DMA
00103
           USART_TX_Buffer(&serial, (uint8_t *)&TRX_Buffer[0], len);
00104
00105
           va end(args);
00106 }
00107
00124
00125
00126
00137
       int readConsole(const char *msg, ...) {
00138
           va list args:
00139
           int result;
00140
00141
           rx_get_flag = 1; // Enable reception
00142
            // Start DMA reception
00143
00144
           USART RX Buffer(&serial, (uint8 t *) TRX Buffer, RX Buffer Length, 0);
00146
           // Wait until data reception is complete
00147
           while (rx_flag == 0) {
00148
                // Wait loop
00149
           }
00150
00151
           // Check for valid input length
00152
           if (RX_Length < 2) {</pre>
00153
               // Reset flags and return error
00154
                rx_get_flag = 0;
               rx_flag = 0;
return -1;
00155
00156
00157
00158
00159
           // Null-terminate the received string
00160
           TRX_Buffer[RX_Length - 1] = ' \setminus 0';
00161
           \ensuremath{//} Parse the input using the format string
00162
00163
           va start(args, msg);
00164
           result = vsscanf((char *)TRX_Buffer, msg, args);
00165
           va_end(args);
00166
00167
           // Reset reception flags
           rx_get_flag = 0;
00168
00169
           rx_flag = 0;
00170
00171
           return result;
00172 }
```

3.2 Console.h File Reference

Console Interface for STM32F407VGT6.

```
#include "main.h"
#include "GPIO/GPIO.h"
#include "USART/USART.h"
#include "DMA/DMA.h"
Include dependency graph for Console.h:
```

3.3 Console.h

3.3 Console.h

Go to the documentation of this file.

```
00001
00073 #ifndef CONSOLE_H_
00074 #define CONSOLE_H_
00075
00076 #include "main.h"
00077 #include "GPIO/GPIO.h"
00078 #include "USART/USART.h"
00079 #include "DMA/DMA.h"
00080
00089 void Console_Init(int32_t baudrate);
00090
00100 void printConsole(char *msg, ...);
00101
00113 int readConsole(const char *msg, ...);
00114
00115 #endif /* CONSOLE_H_ */
00116
```

10 File Documentation

Index

Console Module for STM32F407VGT6, 3 Console.h, 8